

# Set up the log

Set up the audit log

Version 8.0



This documentation is provided under restrictions on use and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this documentation, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

# Table of Contents

Set up the audit log

4

# Set up the audit log

PRODUCTS: **ALL CREATIO PRODUCTS**

The **audit log** records system settings, events, and data. It logs events related to changes in the user role structure, the distribution of access permissions, changes in the system setting values, user authorization in Creatio, etc.

The **change log** records changes to business data. You can use it to track product price or account balance changes. Learn more: [Set up the change log](#).

**Note.** Enable the “View “Audit log” section” (“CanViewSysOperationAudit” code) system operation to view the audit log. Enable the “Manage “Audit log” section” (“CanViewSysOperationAudit” code) system operation to view and archive the audit log records. Learn more: [System operation permissions](#).

The audit log is disabled by default. Follow the steps in this article to enable this feature.

To enable the audit log using the system settings:



1. Click the  button to open the System designer.
2. Click “System settings” in the “System setup” block.
3. Select the “Audit log” folder subordinate to the “Administration” folder. This folder contains all system settings that control the audit log. Each logged event type has a dedicated system setting that enables or disables it. Learn more about the audit log system settings: [Description of system settings](#).
4. Open the setting and select the [ *Default value* ] checkbox to enable it. For example, select the checkbox in the [ *Log user authorization management events* ] system setting (Fig. 1) to record user log in and log out events.

Fig. 1 An audit log system setting



Log user authorization management events

CLOSE

Name\* Log user authorization management events

Type\* Boolean

Code\* UseUserAuthorizationLog

Default value

Cached

Personal

Allow for portal users

Description

---

After disabling an audit log system setting, you may need to restart the Redis session server for the changes to take effect.

**Note.** If the audit log is enabled on the configuration file level, Creatio will ignore the system setting values.